

CSE3213 Computer Network I

Network Layer
(7.1, 7.3, 8.2.1-8.2.3)

Course page:
<http://www.cse.yorku.ca/course/3213>


Slides modified from Alberto Leon-Garcia and Indra Widjaja and Jim Kurose

Network Layer

- Introduction
- Virtual circuit and datagram networks
- IP: Internet Protocol
 - Datagram format
 - IPv4 addressing

Network layer

- transport segment from sending to receiving host
- on sending side encapsulates segments into datagrams
- on rcving side, delivers segments to transport layer
- network layer protocols in *every* host, router
- router examines header fields in all IP datagrams passing through it




Two Key Network-Layer Functions

- *forwarding*: move packets from router's input to appropriate router output
- *routing*: determine route taken by packets from source to dest.
 - *routing algorithms*

analogy:

- *routing*: process of planning trip from source to dest
- *forwarding*: process of getting through single interchange

Interplay between routing and forwarding



Connection setup

- 3rd important function in *some* network architectures:
 - ATM, frame relay, X.25
- before datagrams flow, two end hosts *and* intervening routers establish virtual connection
 - routers get involved
- network vs transport layer connection service:
 - **network**: between two hosts (may also involve intervening routers in case of VCs)
 - **transport**: between two processes

Network service model

Q: What *service model* for “channel” transporting datagrams from sender to receiver?

Example services for individual datagrams:

- guaranteed delivery
- guaranteed delivery with less than 40 msec delay

Example services for a flow of datagrams:

- in-order datagram delivery
- guaranteed minimum bandwidth to flow
- restrictions on changes in inter-packet spacing

Network Layer

- Introduction
- Virtual circuit and datagram networks
- What's inside a router
- IP: Internet Protocol
 - Datagram format
 - IPv4 addressing

Network layer connection and connection-less service

- datagram network provides network-layer connectionless service
- VC network provides network-layer connection service
- analogous to the transport-layer services, but:
 - **service:** host-to-host
 - **no choice:** network provides one or the other
 - **implementation:** in network core

Virtual circuits

“source-to-dest path behaves much like telephone circuit”


- performance-wise
 - network actions along source-to-dest path
-
- call setup, teardown for each call *before* data can flow
 - each packet carries VC identifier (not destination host address)
 - *every* router on source-dest path maintains “state” for each passing connection
 - link, router resources (bandwidth, buffers) may be *allocated* to VC (dedicated resources = predictable service)

VC implementation

a VC consists of:

1. path from source to destination
 2. VC numbers, one number for each link along path
 3. entries in forwarding tables in routers along path
- packet belonging to VC carries VC number (rather than dest address)
 - VC number can be changed on each link.
 - New VC number comes from forwarding table

Forwarding table




Forwarding table in
northwest router:

Incoming interface	Incoming VC #	Outgoing interface	Outgoing VC #
1	12	3	22
2	63	1	18
3	7	2	17
1	97	3	87
...	...	...	...

Routers maintain connection state information!


Virtual circuits: signaling protocols

- used to setup, maintain teardown VC
- used in ATM, frame-relay, X.25
- not used in today's Internet



Datagram networks

- no call setup at network layer
- routers: no state about end-to-end connections
 - no network-level concept of "connection"
- packets forwarded using destination host address
 - packets between same source-dest pair may take different paths



Forwarding table

4 billion
possible entries

<u>Destination Address Range</u>	<u>Link Interface</u>
11001000 00010111 00010000 00000000 through 11001000 00010111 00010111 11111111	0
11001000 00010111 00011000 00000000 through 11001000 00010111 00011000 11111111	1
11001000 00010111 00011001 00000000 through 11001000 00010111 00011111 11111111	2
otherwise	3

Datagram or VC network: why?

Internet (datagram)

- data exchange among computers
 - "elastic" service, no strict timing req.
- "smart" end systems (computers)
 - can adapt, perform control, error recovery
 - simple inside network, complexity at "edge"
- many link types
 - different characteristics
 - uniform service difficult

ATM (VC)


- evolved from telephony
- human conversation:
 - strict timing, reliability requirements
 - need for guaranteed service
- "dumb" end systems
 - telephones
 - complexity inside network

Network Layer

- Introduction
- Virtual circuit and datagram networks
- **IP: Internet Protocol**
 - Datagram format
 - IPv4 addressing

The Internet Network layer

Host, router network layer functions:



Network Layer

- Introduction
- Virtual circuit and datagram networks
- IP: Internet Protocol
 - Datagram format
 - IPv4 addressing

IP datagram format

IP protocol version
number

header length
(bytes)


"type" of data

max number
remaining hops
(decremented at
each router)

upper layer protocol
to deliver payload to

how much overhead with TCP?

- 20 bytes of TCP
- 20 bytes of IP
- = 40 bytes + app layer overhead




total datagram
length (bytes)

for
fragmentation/
reassembly

E.g. timestamp,
record route
taken, specify
list of routers
to visit.

IP Fragmentation & Reassembly

- network links have MTU (max.transfer size) - largest possible link-level frame.
 - different link types, different MTUs
- large IP datagram divided ("fragmented") within net
 - one datagram becomes several datagrams
 - "reassembled" only at final destination
 - IP header bits used to identify, order related fragments



IP Fragmentation and Reassembly

Example

- 4000 byte datagram
- MTU = 1500 bytes

1480 bytes in data field

offset = $1480/8$

	length	ID	fragflag	offset	
	=4000	=x	=0	=0	

One large datagram becomes several smaller datagrams

	length	ID	fragflag	offset	
	=1500	=x	=1	=0	

	length	ID	fragflag	offset	
	=1500	=x	=1	=185	


	length	ID	fragflag	offset	
	=1040	=x	=0	=370	

Network Layer

- Introduction
- Virtual circuit and datagram networks
- IP: Internet Protocol
 - Datagram format
 - IPv4 addressing


Classful Addresses

Class A



- 126 networks with up to 16 million hosts **1.0.0.0 to 127.255.255.255**

Class B



- 16,382 networks with up to 64,000 hosts **128.0.0.0 to 191.255.255.255**

Class C



- 2 million networks with up to 254 hosts **192.0.0.0 to 223.255.255.255**

Class D

28 bits

1	1	1	0	multicast address
---	---	---	---	-------------------

224.0.0.0 to
239.255.255.255

- Up to 250 million multicast groups at the same time
- Permanent group addresses
 - All systems in LAN; All routers in LAN;
 - All OSPF routers on LAN; All designated OSPF routers on a LAN, etc.
- Temporary groups addresses created as needed
- Special multicast routers

Reserved Host IDs (all 0s & 1s)

Internet address used to refer to network has hostid set to all 0s

0	0	0	0							0	0
---	---	---	---	--	--	--	--	--	--	---	---

this host
(used when
booting up)

0	0		0	host							
---	---	--	---	------	--	--	--	--	--	--	--

a host
in this
network

Broadcast address has hostid set to all 1s

1	1	1	1							1	1
---	---	---	---	--	--	--	--	--	--	---	---

broadcast on
local network


netid				1	1	1				1	1	1	1
-------	--	--	--	---	---	---	--	--	--	---	---	---	---

broadcast on
distant
network

Private IP Addresses

- Specific ranges of IP addresses set aside for use in private networks (RFC 1918)
- Use restricted to private internets; routers in public Internet discard packets with these addresses
- Range 1: 10.0.0.0 to 10.255.255.255
- Range 2: 172.16.0.0 to 172.31.255.255
- Range 3: 192.168.0.0 to 192.168.255.255
- Network Address Translation (NAT) used to convert between private & global IP addresses

Example of IP Addressing



Address with host ID=all 0s refers to the network

Address with host ID=all 1s refers to a broadcast packet

R = router

H = host₂₈

Subnet Addressing

- Subnet addressing introduces another hierarchical level
- Transparent to remote networks
- Simplifies management of multiplicity of LANs
- Masking used to find subnet number

Original
address

1	0	Net ID	Host ID
---	---	--------	---------

Subnetted
address

1	0	Net ID	Subnet ID	Host ID
---	---	--------	-----------	---------

Subnetting Example

- Organization has Class B address (16 host ID bits) with network ID: 150.100.0.0
- Create subnets with up to 100 hosts each
 - 7 bits sufficient for each subnet
 - $16-7=9$ bits for subnet ID
- Apply subnet mask to IP addresses to find corresponding subnet
 - Example: Find subnet for 150.100.12.176
 - IP add = 10010110 01100100 00001100 10110000
 - Mask = 11111111 11111111 11111111 10000000
 - AND = 10010110 01100100 00001100 10000000
 - Subnet = 150.100.12.128
 - Subnet address used by routers within organization

Subnet Example

